How can I swap the scanning order - ecCodes GRIB FAQ

How do I swap (reverse) the scanning order? for example changing north-to-south to south-to-north

Step-by-step guide

Say you have a GRIB file with scanning order of south-to-north (for latitudes). This means the key "jScansPositively" is 1. You want to change this to north-to-south i.e. jScansPositively should become 0

1. Ensure that the grid geometry of your GRIB message specifies **both** the latitudes:

 $latitude Of First Grid Point In Degrees\ and\ latitude Of Last Grid Point In Degree Of Las$

2. Check what scanning modes you have in your input file:

```
% grib_ls -p jScansPositively,iScansPositively input.grib
```


3. Use the grib_set command to swap the scanning order for the latitudes:

```
% grib_set -s swapScanningY=1 input.grib output.grib
```

This changes the order in which the data is stored in the GRIB message

There is also the key "swapScanningX" to do the same task for longitudes (east-to-west changed to west-to-east).

Here is a way of visualising the different scanning orders:



The swapScanningX/Y keys only work for regular lat/lon grids and regular Gaussian grids. It is not to be used for reduced grids, Lambert, Polar stereographic, Mercator etc

Check the output GRIB file to ensure the data is shown correctly e.g., by plotting it

Related articles

- Why do I get a bitmap even though none of my values are missing ecCodes GRIB FAQ
- Memory-based access to definition/sample files (MEMFS) ecCodes FAQ
- How do I use an OR condition (logical disjunction) in a where clause ecCodes GRIB FAQ
- How can I find out which keys can be set to "missing" ecCodes GRIB FAQ
- Creating your own local definitions ecCodes GRIB FAQ